

## Read Me First BEFORE You Turn on the Computer

### Updating the Atheros® AR5004X/AR5004G Wireless Network Adapter Software on Your Toshiba Computer

---

For systems with the Atheros AR5004X/AR5004G wireless network adapter, turning the wireless antenna switch on or off while your computer is in Suspend or Hibernation Mode may prevent the wireless device from operating when you Resume using the computer.

To correct this situation, you will need to update the wireless adapter driver using the following procedure:

---

**NOTE**

If you are recovering your system using the Recovery media that shipped with your computer, be sure to use this procedure to update the wireless network adapter driver after completing the recovery.

- 
- 1 Log onto the computer with Administrator privileges.

(continued on back)

- 2 Insert the “Atheros AR5004X/AR5004G Wireless Network Adapter Software CD V1.00” (shipped with your system) into your computer’s optical drive.
- 3 Select **Start, Control Panel, Performance and Maintenance**, and then **System**.
- 4 Select the **Hardware** tab and click **Device Manager**.
- 5 Select **Network adapters**, and highlight either the “Atheros AR5004X Wireless Network Adapter” or “Atheros AR5004G Wireless Network Adapter (depending on your computer’s configuration).”
- 6 Right click on the adapter and select **Update Driver** to start the Hardware Update Wizard.
- 7 Select “Install from a list or specific location (Advanced)” and click **Next**.
- 8 Select “Include this location in the search:” and type D:\Driver\WinXP in the box.
- 9 Click **Next**.
- 10 Follow the on-screen instructions and then click **Finish** when a message indicates that the Setup has completed.
- 11 Remove the CD.
- 12 Restart the computer.